








Pattern

1/4



1 How to knit (Full needle rib) tailored collar

- ① Arrange the needles for the pattern as the diagram on previous page.
- ② Work the collar in the same manner as for the shawl collar. For the lapel refer to figure A.



- ③ After working the shaping by partial knitting, knit 1 row across all stitches.
- ④ Then using a piece of waste yarn, knit 1 row around on KH and KR by hand.
- ⑤ Leaving a loop of yarn about 30 cm long hanging down, knit to the right. Continue partial knitting of the increases as shown in the diagram. Decreases are worked in the same manner as for the shawl collar.

★ The looped yarn in 5 is used to finish the lapel.

- ⑥ After both sides of collar are completed, press the lapel only, very lightly with a steam iron. Unravel the waste yarn. The two edges of the lapel are separated now. Finish the decreased part in ribbing, and for the increased part, pass the yarn twice through the stitches. Block lightly with a steam iron in the shape of the pattern.

2 How to attach the collar

Do same as for the shawl collar.





**1 · alza gli ultimi due aghi e comincia a modellare
il risvolto in modalità aghi sospesi**

passa il carrello a sinistra



**2 · passa il filo dietro all'ago
per evitare il buco**

passa il carrello a destra




si forma un doppio loop




**3 · alza i due aghi successivi
e ripeti i passaggi 1 e 2**



**4 · quando hai finito, ripassa il carrello
a sinistra, lavorando tutti gli aghi**




4 · così




**5 · ora lavora manualmente gli
stessi aghi in tubolare, con un filo
di scarto**


sulla seconda frontura...




... e poi nella prima frontura

**6 · ora, prima di passare il carrello
a destra, tira in basso il filo
principale per circa 30 cm: ti
servirà per rifinire i bordi del rever**





7 · passa il carrello a destra



**8 · alza gli aghi per modellare la parte alta
del risvolto, sempre ad aghi sospesi**

passa il carrello a destra



8 · fai passare il filo dietro all'ago, per evitare i buchi...




... in questo modo


e passa il carrello a destra



**così è come appare l'ago con il filo
accavallato**



**9 · ripeti gli ultimi due passaggi su tutti gli
aghi sospesi, lavorandoli a due a due**



gli ultimi due aghi




**10 · ora continua a modellare il risvolto diminuendo
con il punzone, come da cartamodello**



11 · il campione tolto dalla macchina



**12 · blocca le maglie svaporando sui punti
dove c'è filo di scarto**



13 · ora puoi sfilare il filo di scarto e chiudere a mano i punti aperti





chiusura tubolare



